



# KONICA MINOLTA

## DiIMAGE Scan Dual IV Ver.1.0.3

### 1. Main Changes

#### **Windows**

- Corrected the problem that Auto Dust Brush fails to work against scanned images of 16-bit colour depth.

#### **Macintosh**

- Corrected the problem that the Quick Scan button of the scanner hardware cannot be used under Mac OS X v10.4.

*<Decompressing the downloaded file with Mac OS X v10.4>*

The StuffIt Expander does not come with Mac OS X v10.4. For details, please visit the information from Apple Computer, Inc. shown below:  
<http://docs.info.apple.com/article.html?artnum=301016>

If no decompressing application is included in the computer, please install separately.

### 2. System requirements

For each compatibility of the products in the following table (OS, interface board, application), please consult the manual supplied with each device and contact the manufacturer directly.

**<Windows>**

Computer[CPU(*1)]	IBM PC/AT compatible computer with a Pentium Processor 166MHz or higher.
Operating System	Windows 98 Windows 98 Second Edition Windows Me Windows 2000 Professional Windows XP Professional Windows XP Home Edition
Memory(*1)	64MB or more of RAM
Monitor	800 x 600 monitor capable of displaying High Color (16 bit) is required. 1024 x 768 monitor is recommended.
Hard Disk Space	300MB or more of available hard-disk space is required.
Tested Application (*2)	Adobe Photoshop 6.0.1, 7.0.1, CS, CS2, Adobe Photoshop Elements 2.0, 3.0, PaintShopPro 8, Corel PHOTO-PAINT 11
Recommended Board(*2)	Adaptec, Inc.: USB2connect 3100, USB2connect 5100, DuoConnect Belkin: Hi-speed USB2.0 5-Port PCI Card, USB2.0 Hi-speed 2-Port PCI Card Preinstalled USB port.

**< 16-bit output with Auto Dust Brush >**

CPU:Pentium 166MHz or later, Pentium III or later recommended. / RAM: 128MB or more, 256MB or more recommended. / Hard Disk Space: 1GB or more, 2GB or more recommended.

**<Macintosh>**

Computer[CPU(*1)]	Apple Macintosh with a built-in USB port as standard interface and with a PowerPC G3 or higher.
Operating System	Mac OS 8.6 to 9.2.2, Mac OS X v10.1.3 to 10.1.5, v10.2.1 to 10.2.8, v10.3 to 10.3.9, v10.4 to 10.4.3
Memory	A minimum of 64MB of RAM in addition to the requirements for the Mac OS and applications.
Monitor	800 x 600 monitor capable of displaying at least 32,000 colors is required. 1024 x 768 monitor is recommended.
Hard Disk Space	300MB or more of available hard-disk space is required.
Tested Application (*2)	Adobe Photoshop 6.0.1, 7.0.1, CS, CS2, Adobe Photoshop Elements 2.0, 3.0
Recommended Board(*2)	Preinstalled USB port.

**< 16-bit output with Auto Dust Brush >**

CPU:PowerPC G3 or higher, PowerPC G4 or higher recommended. / RAM: At least 128 MB of RAM. (256 MB or more recommended) / Hard Disk Space:1GB or more, 2GB or more recommended.

\*1: Necessary to meet the requirements recommended for use with the OS.

\*2:Operation must be guaranteed by the manufacturers when used with the OS. For details, please ask their respective manufacturers.

For compatibility information of other interface board, refer to compatibility information page.

### **3. Installation Procedure**

#### **Windows**

- On Windows XP and 2000 Professional, the administrator privilege is required to install the driver.
- In case that a restart-computer message appears after completing uninstallation of previous version or installation of this version, restart the computer.

#### **Full download**

1. Create a new work directory (folder) on your computer.
2. Download a desired driver (dd4103e.exe) to the folder created in step 1.
3. Double click on "dd4103e.exe". Confirmation screen\* appears.
4. Click [OK].
5. Confirm the folder to extract the installer file and click [Extract].  
(Default setting is the folder you created in step 1.)  
The self-extracting file creates "Setup.exe" and "ADBSetup.exe".
- 6-1. Driver software Installation.

If the previous version is pre-existing:

1. Select Remove DiMAGE Scan Dual4 from the DiMAGE Scan Dual4 ver.1.0 folder in the program option of the start menu.

Simply follow the instructions in the windows to complete uninstallation.

2. Double-click on "Setup.exe". The installer program starts installation.

If the driver software is newly installed:

Double-click on "Setup.exe". The installer program starts installation.

Refer to the installation instruction in the instruction manual to complete.

- 6-2. Auto Dust Brush Plug-in Installation.

If the previous version is pre-existing:

1. Double-click on "ADBSetup.exe".

Simply follow the instructions in the windows to complete uninstallation.

2. Double-click on "ADBSetup.exe" again. The installer program starts installation.

If the Auto Dust Brush Plug-in is newly installed:

Double-click on "ADBSetup.exe". The installer program starts installation.

Refer to the Auto Dust Brush Plug-in installation instruction in the instruction manual to complete.

- When installing Auto Dust Plug-in in Adobe Photoshop CS2, the "Unable to find Adobe Photoshop Elements 2.0. ... continue the installation?" message appears. Click on "Yes" to continue. As the folder selection window opens, specify Plug-ins folder of Adobe Photoshop CS2.

\*Displayed in English.

#### **Split download**

Note: Please carefully read the instruction below before downloading. Download each files to the same folder without extracting.

1. Create a new work directory (folder) on your computer.
2. Download all the desired split files ("dd4103e1.exe", "dd4103e2.zip", "dd4103e3.zip") to the folder created in step 1.

Note: Download each files to the same folder without extracting.

3. Double click on "dd4103e1.exe". Confirmation screen\* appears.

4. Click [OK].

5. Confirm the folder to extract the installer file and click [Extract].

(Default setting is the folder you created in step 1.)

The self-extracting file creates "Setup.exe" and "ADBSetup.exe".

- 6-1. Driver software Installation.

If the previous version is pre-existing:

- 1) Select Remove DiMAGE Scan Dual4 from the DiMAGE Scan Dual4 ver.1.0 folder in the program option of the start menu.

Simply follow the instructions in the windows to complete uninstallation.

- 2) Double-click on "Setup.exe". The installer program starts installation.

If the driver software is newly installed:

Double-click on "Setup.exe". The installer program starts installation.

Refer to the installation instruction in the instruction manual to complete.

#### 6-2. Auto Dust Brush Plug-in Installation.

If the previous version is pre-existing:

1) Double-click on "ADBSetup.exe".

Simply follow the instructions in the windows to complete uninstallation.

2) Double-click on "ADBSetup.exe" again. The installer program starts installation.

If the Auto Dust Brush Plug-in is newly installed:

Double-click on "ADBSetup.exe". The installer program starts installation.

Refer to the Auto Dust Brush Plug-in installation instruction in the instruction manual to complete.

- When installing Auto Dust Plug-in in Adobe Photoshop CS2, the "Unable to find Adobe Photoshop Elements 2.0. ... continue the installation?" message appears. Click on "Yes" to continue. As the folder selection window opens, specify Plug-ins folder of Adobe Photoshop CS2.

\*Displayed in English.

Be sure to read the "readme.txt" file before using.

Please use the logging in as Administrator.

### **Macintosh**

- The StuffIt Expander does not come with Mac OS X v10.4. For details, please visit the information from Apple Computer, Inc. shown below:  
<http://docs.info.apple.com/article.html?artnum=301016>
- If no decompressing application is included in the computer, please install separately.
- On Mac OS X, the administrator privilege is required to install the driver.
- In case that a restart-computer message appears after completing uninstallation of previous version or installation of this version, restart the computer.

### **Full download**

1. Create a new work directory (folder) on your computer.
2. Download a desired driver (dd4103e.sit.hqx) and save it to the folder created in step 1. "DS Dual4 Installer" may appear automatically after downloading depending on the browser settings. In this case, step 3 is not necessary. Please skip to step 4.
3. Use unstuffing utility such as Stuffit Expander to decompress the components. "dd4103e.sit" will be extracted and then "DS Dual4 Installer" will appear.
4. If the previous version is pre-existing:
  - 1) Double click on "DS Dual4 Installer".
  - 2) Click the continue button on the installer screen to begin the installation routine.
  - 3) The end-user license agreement appears. If you accept the terms of the agreement, click the accept button to continue the installation routine. If you do not agree to the conditions, click the decline button and the software will not be installed.
  - 4) Select uninstall from the list box at the top left of the installer dialog box. Confirm the location of the software. Click the uninstall button to remove the software from the computer.
  - 5) Double click on "DS Dual4 Installer" again. The installer program starts installation.

If the driver software is newly installed:

Double-click on "DS Dual4 Installer". The installer program starts installation.

Refer to the installation instruction in the instruction manual to complete.

## Split download

Note: Please carefully read the instruction below before downloading. Be sure to download "dd4103e.sit.1.hqx" last.

1. Create a new work directory (folder) on your computer.
2. Download all the desired split files ("dd4103e.sit.2.hqx" to "dd4103e.sit.8.hqx") to the folder created in step 1.
3. Download "dd4103e.sit.1.hqx" last.
  - All the files may be extracted and combined automatically at downloading and "DS Dual4 Installer" may appear after downloading depending on the browser settings. In this case, steps 4 to 5 are not necessary. Please skip to step 6.
  - In case that all files from "dd4103e.sit.2" to "dd4103e.sit.8" already appear on the screen, step 4 is not necessary. Skip to step 5.
4. Use unstuffing utility such as Stuffit Expander to decompress "dd4103e.sit.2.hqx" to "dd4103e.sit.8.hqx" .  
The files "dd4103e.sit.2" to "dd4103e.sit.8" will appear.
5. Use unstuffing utility such as Stuffit Expander to decompress "dd4103e.sit.1.hqx". (In case that "dd4103e.sit.1" appears, decompress it.)  
When decompressing "dd4103e.sit.1.hqx":  
This extracts "dd4103e.sit.1", and then combines all the files "dd4103e.sit.1" to "dd4103e.sit.8" to create "dd4103e.sit" and extracts "DS Dual4 Installer" automatically.  
When decompressing "dd4103e.sit.1":  
Decompressing "dd4103e.sit.1" combines all the files "dd4103e.sit.1" to "dd4103e.sit.8" to create "dd4103e.sit" and extracts "DS Dual4 Installer" automatically.
6. If the previous version is pre-existing:
  - 1) Double click on "DS Dual4 Installer".
  - 2) Click the continue button on the installer screen to begin the installation routine.
  - 3) The end-user license agreement appears. If you accept the terms of the agreement, click the accept button to continue the installation routine. If you do not agree to the conditions, click the decline button and the software will not be installed.
  - 4) Select uninstall from the list box at the top left of the installer dialog box. Confirm the location of the software. Click the uninstall button to remove the software from the computer.
  - 5) Double click on "DS Dual4 Installer" again. The installer program starts installation.If the driver software is newly installed:  
Double-click on "DS Dual4 Installer". The installer program starts installation.

Refer to the installation instruction in the instruction manual to complete.

Be sure to read the "readme" file before using.

Please use by logging in with the name used at installation.